

Currently Cited Test Methods for Adhesives

1. USEPA Method 24
2. Exempt Compounds By SCAQMD Method 303
3. VOC Of PVC, CPVC, ABS Pipe Cements, And Adhesive Primer By Method 316A
4. VOC Of Cyanoacrylate Adhesives By Method 316B

1


USEPA Method 24 Determination of Volatile Matter Content

Default VOC Determination Method:
Ambient Cure

Dispersion Without A Diluent?
Use A Paperclip!

Induction Time - 24 Hour Default

Analyzed In Tandem With SCAQMD M303



2

SCAQMD M303 Determination of Exempt Compounds



Performed on GC-MS/FID

Challenging
Sample Introduction

Exempts Subtracted From
VOC Calculation

3

VOC of Material Calculation (Actual VOC):

$$VOC_{material} = (100 - 48 - 50) \times 0.99 \times 10 = 20g/L$$



VOC of Coating Calculation (Regulatory VOC, less water and exempt compounds):

Remove the volume solid from denominator
Volume Solids = [Weight Solids]/[Density]

$$VOC_{coating} = \frac{(100 - 48 - 50)}{\left(\frac{100}{0.99} - \frac{50}{0.97}\right)} \times 1000 = 39g/L$$



VOC Calculation

VOC of Material

$$\frac{W_s - W_w - W_{es}}{V_m}$$

VOC Of Regulated Product (Less Water And Exempts)

$$\frac{W_s - W_w - W_{es}}{V_m - V_w - V_{es}}$$

4

Additional Test Methods

VOC Of PVC, CPVC, And ABS Pipe Cements
Adhesive Primer By **Method 316A**

VOC Of Cyanoacrylate Adhesives By Method 316B

5

Method 316A

VOC Used In Materials For Pipes And Fittings

Used For PVC/ABS Systems

8 Replicate Preps Per Sample;
Time And Effort Intensive


Precision Lacking Compared To M24



6

Method 316B

VOCs in Adhesives Containing Cyanoacrylates



“Sandwich” Test Method

Aluminum Sheets Simulate
Traditional Curing Conditions

Utilizes Spacers To Prevent
“Squish” Effect From Clamps

7

Proposed Methods

Modification of EPA 40 CFR Appendix A Subpart PPPP

“Determination Of VOCs For Reactive Adhesives”

24 Hour Cure By Default

“Sandwich” Test Method With 3x3 Inch Aluminum Or Plastic Sheets

Not Applicable For Cyanoacrylates, Moisture-Cured Urethanes,
or Silicone Adhesives

Sample Size (10 - 15 g) And Sandwich Material Considerations

Possible Replacement For 316A And Others; Lacks QC,
Bias, Precision, Repeatability, And Reproducibility Data

8

Method 313
VOCs By GC/MS/FID

	Gravimetric Methods	Direct Method
Quantitation Tactic	Assume 100% VOC; Deduct Non-VOC	Quantitate All Sample Peaks
Exempts Handling	Measure And Discount	Ignore


9

Method 313
VOCs By GC/MS/FID

Advantages	Disadvantages
Direct VOC Measurement; Increased Accuracy	Not For Multi-Component Products
High Precision At Low Concentrations	Difficult Sample Introduction For Adhesives
High Degree of Quality Control	Must Cure In Inlet; Discount Unreacted Monomer


10

Polyurethane Foam Adhesive
Test Method Concept




11

Polyurethane Foam Adhesive
Test Method Concept



12



Brad Parrack
Senior Air Quality Chemist
909.396.3071
bparrack@aqmd.gov